



TEC-IT

TBarCode OCX

Barcode ActiveX® Control

Version 8.0

User Manual

23 October 2007

TEC-IT Datenverarbeitung GmbH
Wagnerstrasse 6
A-4400 Steyr, Austria

t ++43 (0)7252 72720
f ++43 (0)7252 72720 77
office@tec-it.com
www.tec-it.com
Content

WWW.TEC-IT.COM



1 Content

1	Content	2
1.1	List of Figures	4
1.2	List of Tables	5
2	Disclaimer	6
3	Introduction	7
3.1	What is TBarCode?	7
3.2	What is TBarCode OCX?	7
3.3	Scope of this Document	7
3.4	Restrictions of the Demo Version	8
3.5	Important Security Notice	8
4	Installation	9
4.1	Requirements	9
4.2	Download and Setup	9
5	Insert Barcode	10
5.1	General	10
5.2	Insert Barcode using the Menu	10
5.3	Insert Barcode using the Control Toolbox	11
5.4	Insert Barcode per Code	11
6	Adjust Barcode Parameters	12
6.1	General	12
6.2	Activate the Design Mode	12
6.2.1	Microsoft Word or Excel	12
6.2.2	Microsoft Access	12
6.3	Barcode Parameters	13
6.3.1	Property Pages	13
6.3.2	Property List	14
6.3.3	Adjust Parameters per Code	14
7	Set Barcode Data (Data Binding)	15
7.1	General	15
7.2	Specify Data Manually	15
7.2.1	Property Pages	15
7.2.2	Property List	15
7.3	Data Binding	15
7.3.1	Microsoft Excel	16
7.3.2	Microsoft Access	16
7.3.3	Specify Data via VBA Code	17
8	Programming TBarCode (VBA)	18
8.1	General	18
8.2	Microsoft Office and VBA	18
8.3	Insert Barcode	18
8.3.1	Microsoft Word	19
8.3.2	Microsoft Excel	19
8.4	Adjust Barcode Parameters and Barcode Data	20
8.4.1	Microsoft Word or Excel	20
8.4.2	Microsoft Access	20
8.5	License TBarCode	20
9	The TBarCode Office Add-In	21
9.1	General	21
9.2	Insert Barcode using the TBarCode Toolbar	21
9.3	Adjust Barcode Parameters using the Toolbar	22
9.4	Serial Letter Command	22
10	Barcodes in Microsoft InfoPath®	24
10.1	General	24
10.2	Activate the Design Mode	24
10.3	Add TBarCode to the Custom Controls	25
10.3.1	Specify Data Source Type	26
10.3.1.1	Encode Single Data Fields	27
10.3.1.2	Encode Complete or Partial Form Content (XML Data)	27
10.3.2	Finish Adding the Custom Control	28
10.4	Insert Barcode	29
10.5	Change Binding	30
10.6	Adjust Barcode Parameters	30
10.7	Multiple Barcodes	31

11	The Property Pages	32
11.1	Introduction	32
11.2	Property Page "Barcode"	32
11.2.1	Barcode Type (Symbology)	32
11.2.2	Button "Adjust..."	32
11.2.3	Barcode Data	33
11.2.4	Encoding Mode	33
11.2.5	Code page	33
11.2.6	Format/Subset	33
11.2.7	Check Digit	34
11.2.7.1	Check Digit Override	34
11.2.8	Compression	34
11.2.9	Suppress Error Messages	35
11.2.10	Translate Escape Sequences	35
11.2.11	Button "License..."	35
11.2.12	Button "About..."	35
11.3	Property Page "Appearance"	36
11.3.1	General	36
11.3.1.1	Orientation	36
11.3.1.2	Print Ratio	36
11.3.1.3	Back Style	37
11.3.1.4	Notch Height [1/1000 mm]	37
11.3.1.5	Bearer Bars	37
11.3.1.6	Bearer Bar Width [1/1000 mm]	37
11.3.1.7	Draw Mode	37
11.3.1.8	Quiet Zone [modules]	38
11.3.2	Text Options	38
11.3.2.1	Print Text	38
11.3.2.2	Above Symbol	38
11.3.2.3	Alignment	38
11.3.2.4	Text Distance	38
11.3.3	Barcode Size and Module Width	38
11.3.3.1	Mode	38
11.3.3.2	Module Width [1/1000 mm]	39
11.3.3.3	Resolution	39
11.3.3.4	Custom Resolution (DPI)	40
11.3.3.5	Decoder	40
11.3.4	Display Error if Barcode is Clipped	40
11.4	Property Page "Multiple Barcodes"	41
11.4.1	Enable Multiple Barcodes	41
11.4.2	Number of Barcodes	41
11.4.3	Minimum Barcode Distance [1/1000 mm]	42
11.4.4	Data Limit per Barcode [Bytes]	42
11.4.5	Structured Append	42
11.4.6	Dynamic Bounding Rectangle	43
11.5	Property Page "Font"	44
11.5.1	Properties	44
11.5.2	Font	44
11.5.3	Size	44
11.5.4	Effects	44
11.5.5	Sample Text	44
11.6	Property Page "Color"	45
11.6.1	Properties	45
11.6.2	Color Set	45
11.6.3	Color Palette	45
11.6.4	Edit Custom Color...	45
11.7	Adjust...	46
11.8	Adjust Properties: Aztec Code	47
11.8.1	Format / format specifier	47
11.8.2	Symbol Size	47
11.8.3	Enforce binary encoding	47
11.8.4	Enable Aztec Runes	47
11.8.5	Error Correction in % [0-90]	48
11.8.6	Structured Append	48
11.8.6.1	Use structured append	48
11.8.6.2	Number of all symbols [A...Z]	48
11.8.6.3	Index of this symbol [1...16]	48
11.8.6.4	Message ID	48
11.9	Adjust Properties: Codablock-F	49
11.9.1	Rows [2..44]	49
11.9.2	Columns [4..62]	49
11.9.3	Row height [1/1000 mm]	49
11.9.4	Separator height [1/1000 mm]	49
11.9.5	Code format	49

11.10	Adjust Properties: Data Matrix	50
11.10.1	Code Format	50
11.10.2	Symbol Size	50
11.10.3	Show as Rectangle	50
11.10.4	Structured Append	50
11.10.4.1	Use structured append	50
11.10.4.2	Number of all symbols [2...16]	51
11.10.4.3	Index of this symbol [1...16]	51
11.10.4.4	File-ID [1...64516]	51
11.11	Adjust Properties: MaxiCode	52
11.11.1	Mode	52
11.11.2	Undercut [0..100 %]	52
11.11.3	Preamble Options	52
11.11.3.1	Use Preamble	53
11.11.3.2	Preamble date (0...99)	53
11.11.4	Structured Append	53
11.11.4.1	Use structured append	53
11.11.4.2	Number of all symbols [2...8]	53
11.11.4.3	Index of this symbol [1...8]	53
11.11.5	Structured Carrier Message (SCM)	53
11.11.5.1	Service class [0...999]	53
11.11.5.2	Country code [0...999]	53
11.11.5.3	Postal code [9 digits]	53
11.12	Adjust Properties: PDF417	54
11.12.1	PDF417	54
11.12.1.1	Rows [3..90]	54
11.12.1.2	Row height [1/1000 mm]	54
11.12.1.3	Columns [1..30]	55
11.12.1.4	Error Correction Level	55
11.12.1.5	Encoding Mode	55
11.12.2	MicroPDF417	55
11.12.2.1	Mode	56
11.12.2.2	Version	56
11.12.3	Macro PDF417 (structured append)	56
11.13	Adjust Properties: QR-Code	57
11.13.1	Format / Application Indicator	57
11.13.2	Symbol Version (Size)	57
11.13.3	Error Correction Level	57
11.13.4	Mask Pattern	58
11.13.5	Compaction	58
11.13.6	Structured Append	58
11.13.6.1	Use Structured Append	58
11.13.6.2	Parity Byte [0...255]	58
11.13.6.3	Number of all Symbols [2...16]	59
11.13.6.4	Index of this Symbol [1...16]	59
11.14	Adjust Properties: Composite/RSS	60
11.14.1	Composite Component	60
11.14.1.1	Data Input for the EAN.UCC Composite Symbology	60
11.14.2	Segments per Row	61
12	Licensing	62
12.1	License Types	62
12.2	Entering your License Data	62
12.2.1	License Dialog	62
13	Contact and Support Information	63
Appendix A :	Related Downloads	64
A.1	Developer Manuals	64
A.2	Sample Applications	64
A.3	Barcode Reference	64
Appendix B :	FAQ	65
B.1	General	65
B.2	Mail Merge Documents with Barcodes?	65

1.1 List of Figures

Figure 1: Insert Barcode using the Menu (Microsoft Word)	10
Figure 2: Insert Barcode using the Control Toolbox (Microsoft Word)	11
Figure 3: Property Pages (Microsoft Word)	13
Figure 4: Property List (Microsoft Word)	14

Figure 5: Data Binding in Microsoft Excel	16
Figure 6: Data Binding in Microsoft Access	17
Figure 7: TBarCode Toolbar	21
Figure 8: The Serial Letter Dialog	22
Figure 9: Result of the Serial Letter Function	23
Figure 10: Add TBarCode to the Custom Controls in Microsoft InfoPath (1)	25
Figure 11: Add TBarCode to the Custom Controls in Microsoft InfoPath (2)	26
Figure 12: Add TBarCode to the Custom Controls in Microsoft InfoPath (3)	28
Figure 13: Insert TBarCode in a Microsoft InfoPath Document	29
Figure 14: Adjust Barcode Properties in Microsoft InfoPath	30
Figure 15: Multiple Barcodes in Microsoft InfoPath	31
Figure 16: Property Page "Barcode"	32
Figure 17: Property Page "Appearance"	36
Figure 18: Property Page "Multiple Barcodes"	41
Figure 19: Property Page "Font"	44
Figure 20: Property Page "Color"	45
Figure 21: Adjust...	46
Figure 22: Advanced Properties: Aztec Code	47
Figure 23: Advanced Properties: Codablock-F	49
Figure 24: Advanced Properties: Data Matrix	50
Figure 25: Advanced Properties: MaxiCode	52
Figure 26: Advanced Properties: PDF417	54
Figure 27: Advanced Properties: QR-Code	57
Figure 28: Advanced Properties: Composite/RSS	60

1.2 List of Tables

Table 1: TBarCode Toolbar Description	21
Table 2: Compression	33
Table 3: Compression	35
Table 4: Bearer Bars	37
Table 5: Text Alignment	38
Table 6: Size Mode	39
Table 7: Resolution	40
Table 8: Decoder	40
Table 9: Number of Barcodes	42
Table 10: Structured Append	42
Table 11: Dynamic Bounding Rectangle	43
Table 12: Codablock-F Code Formats	49
Table 13: Data Matrix Code Formats	50
Table 14: MaxiCode Compaction Modes	52
Table 15: PDF417 Error Correction Levels	55
Table 16: Micro PDF417 Compaction Modes	56
Table 17: QR-Code Formats	57
Table 18: QR-Code Error Correction Levels	57
Table 19: QR-Code Mask Patterns	58
Table 20: QR-Code Compaction Modes	58
Table 21: Composite Component Format	60

2 Disclaimer

The actual version of this product (document) is available as is. TEC-IT declines all warranties which goes beyond applicable rights. The licensee (or reader) bears all risks that might take place during the use of the system (the documentation). TEC-IT and its contractual partner cannot be penalized for direct and indirect damages or losses (this includes non-restrictive, damages through loss of revenues, constriction in the exercise of business, loss of business information or any kind of commercial loss), which is caused by use or inability to use the product (documentation), although the possibility of such damage was pointed out by TEC-IT.



We reserve all rights to this document and the information contained therein. Reproduction, use or disclosure to third parties without express authority is strictly forbidden.



Für dieses Dokument und den darin dargestellten Gegenstand behalten wir uns alle Rechte vor. Vervielfältigung, Bekanntgabe an Dritte oder Verwendung außerhalb des vereinbarten Zweckes sind nicht gestattet.

© 1998-2007
TEC-IT Datenverarbeitung GmbH
Wagnerstr. 6

A-4400 Austria
t.: +43 (0)7252 72720
f.: +43 (0)7252 72720 77
<http://www.tec-it.com>

3 Introduction

3.1 What is TBarCode?

TBarCode is a set of professional tools for the generation of barcodes. More than 70 different symbologies (linear as well as 2D or stacked barcode variants) can be printed or exported as graphics file. All industry formats, in the highest possible resolution and quality, are generated.

TBarCode is available in several versions for different operating systems, applications and programming environments. The following versions are included in this setup:

TBarCode OCX	A Microsoft® ActiveX® compliant barcode control. It can be used with Microsoft® Office applications as well as by software developers.
TBarCode .NET	A .NET barcode library for software developers. It includes barcode controls for Windows Forms and ASP.NET 2.0.
TBarCode Library	A DLL for Windows platforms for software developers. (A DLL for Windows CE/Windows Mobile is available on request. Please contact us with your platform details.)

3.2 What is TBarCode OCX?

TBarCode OCX is a Microsoft® ActiveX® compliant barcode control. Such an ActiveX control is sometimes called OLE control or OCX control. In German it is named "Steuerelement".

You can use **TBarCode OCX** in:

- Microsoft® Office: barcodes are embedded into documents, forms or databases easily.
- Development environments: integrate barcodes into your own application(s).
- Report-Generators and Reporting Engines: Enhance the output with barcode functionality.
- Web Applications: Use barcode technique as part of browser-based applications.
- Most programming and script languages.

Examples¹, where you can use **TBarCode OCX** for barcode generation:

- | | | |
|---------------------------|--------------------------------|-------------------------------------|
| ▪ Microsoft Word | ▪ Microsoft ASP (VBscript®) | ▪ Borland Quick Reports® |
| ▪ Microsoft Excel® | ▪ Microsoft Internet Explorer® | ▪ Sybase® Powerbuilder |
| ▪ Microsoft Access® | ▪ Microsoft Visual FoxPro® | ▪ Crystal Reports® 8 |
| ▪ Microsoft InfoPath® | ▪ Microsoft Dynamics Nav® | ▪ ActiveReports (Data Dynamics) |
| ▪ Microsoft SharePoint® | ▪ Navision Financials® | ▪ IBM® Object REXX® |
| ▪ Microsoft Visio® | ▪ PHP 4.x, PHP 5.x | ▪ Alpha Five Database (Xbasic) |
| ▪ Microsoft Visual Basic® | ▪ Borland C++ Builder® | ▪ ASNA Visual RPG® |
| ▪ Microsoft Visual C++® | ▪ Borland Delphi® | ▪ and a lot of more applications... |

3.3 Scope of this Document

This document concentrates on the use of **TBarCode OCX** in Microsoft Office applications.

If you are a software developer and you are interested in integrating barcode features into your own applications, please check out the accompanying developer manuals, developer references and sample applications (Appendix A).

¹ For applications not supporting ActiveX technology you may use other TEC-IT Barcode Tools (e.g. Barcode Studio).

3.4 Restrictions of the Demo Version

In the demo version the barcodes will be drawn with a demo-hint. That means that the word “Demo” or the phrase “www.tec-it.com” is drawn partially over the barcode. The demo-hint does not influence the readability of the barcode in a negative way.

- ▶ In special cases (e.g. very small or high-resolution barcodes) you may want to test the product without restrictions. To obtain a temporary license key contact sales@tec-it.com.
- ▶ For enabling the full-featured version (without the demo hints) you can obtain a license key from TEC-IT (<http://www.tec-it.com/order/>).
- ▶ For more information on licensing **TBarCode**, please refer to chapter 12.

3.5 Important Security Notice

- ▶ Version 8.0 includes a fix which was implemented in response to a security leak (a malicious web-site in conjunction with Internet Explorer and an installed **TBarCode** ActiveX). **Up to now no real threat is known, but it is strongly recommended to update all TBarCode installations as soon as possible.**

4 Installation

4.1 Requirements

The following operating systems are supported:

- Microsoft Windows 98
- Microsoft Windows 98 Second Edition
- Microsoft Windows ME
- Microsoft Windows NT 4
- Microsoft Windows 2000
- Microsoft Windows XP
- Microsoft Windows Server 2003
- Microsoft Windows Vista

TBarCode OCX was tested with the following Microsoft Office versions (in particular with Microsoft Word, Excel, Access, Visio² and InfoPath³):

- Microsoft Office 97⁴
- Microsoft Office 2000
- Microsoft Office 2002/XP
- Microsoft Office 2003
- Microsoft Office 2007

4.2 Download and Setup

Download **TBarCode** from <http://www.tec-it.com/Download> ► *Software* ► *Barcode Tools for Microsoft Windows* and execute the setup application. Depending on your selection one or more of the following components are installed – along with documentations and sample applications:

- **TBarCode OCX**
A barcode ActiveX control for Microsoft Office users and for software developers. User manual and API reference are included in the setup.
- **TBarCode Library**
For software developers. Developer manual and API reference are included in the setup.
- **TBarCode .NET**
For .NET developers. Developer manual and API reference are included in the setup.

- Administrative rights are required to install **TBarCode**.
- **TBarCode OCX** is an ActiveX control. ActiveX controls must be registered within the Microsoft Windows operating system before they can be used. This registration is executed automatically by the setup application. On demand you can register the OCX file manually with the command line tool "*regsvr32.exe*".

² For Office 2003 and higher

³ For Office 2003 and higher

⁴ Excel '97 is only supported by **TBarCode4**

5 Insert Barcode

5.1 General

This and the following chapters will explain how to use **TBarCode** in Microsoft Office applications. For the following three products the usage of the **TBarCode** control is basically the same:

- Microsoft Word
- Microsoft Excel
- Microsoft Access

Using **TBarCode** in Microsoft InfoPath is explained in detail in chapter 10.

5.2 Insert Barcode using the Menu




Figure 1: Insert Barcode using the Menu (Microsoft Word)

Application	How to insert
Word	<ul style="list-style-type: none"> ▪ Select Insert > Object... from the menu (1). ▪ Select TBarCode8 from the list of object types (2) and confirm with OK. ▪ A new barcode object will be inserted (3).
Excel	
Access	<ul style="list-style-type: none"> ▪ Open your report (or form) in the design mode (see 6.2). ▪ Select Insert > ActiveX Control... from the menu. ▪ Select TBarCode8 from the list of object types and confirm with OK. ▪ A new barcode object will be inserted.
InfoPath	Please refer to section 10.4.

5.3 Insert Barcode using the Control Toolbox




Figure 2: Insert Barcode using the Control Toolbox (Microsoft Word)

► Please note: In Word and Excel the toolbar is named "Control Toolbox", in Access just "Toolbox".

Application	How to insert
Word	<ul style="list-style-type: none"> If the <i>Control Toolbox</i> ❶ is not visible, please open it as follows: <ul style="list-style-type: none"> right-click on one of the visible toolbars and select <i>Control Toolbox</i> or select <i>View ► Toolbars ► Control Toolbox</i> from the menu. Click on the <i>More Controls</i> icon ❷. – A list with available controls will appear (see ❸). Select the entry <i>TBarCode8</i>. Now move the mouse cursor to the desired position and click the left mouse button. The <i>TBarCode</i> control ❹ will be inserted.
Excel	
Access	
InfoPath	Please refer to section 10.4.

5.4 Insert Barcode per Code

Using VBA (Visual Basic for Applications) you can insert the barcode per code. For more information, please refer to section 8.3.

6 Adjust Barcode Parameters

6.1 General


TBarCode offers the possibility to change all barcode related settings (barcode type, barcode data, check digit method, barcode appearance, etc.) to your needs. There are three different methods for changing barcode parameters. These methods are explained in section 6.3.

- Please keep in mind:
In order to select, move, resize, edit and program the **TBarCode** control you have to be in *Design Mode*. When leaving the design mode, the control is locked and can not be edited.

6.2 Activate the Design Mode

Application	How to activate the Design Mode
Word	See section 6.2.1.
Excel	
Access	See section 6.2.2.
InfoPath	See section 10.2.

6.2.1 Microsoft Word or Excel




Switch to *Design Mode* by clicking on the triangle symbol ❶ in the *Control Toolbox*.

If the control toolbox is not visible, please open it as follows:

- Right-click on one of the visible toolbars and select *Control Toolbox* or
- Select *View ► Toolbars ► Control Toolbox* from the menu.

6.2.2 Microsoft Access



You can activate the *Design Mode* when opening the form (or report):

- Select the desired form (or report) and click on the *Design* button ❶ or
- Right-click on the form/report name and select *Design View* (❷) from the pop-up menu.

6.3 Barcode Parameters

The barcode parameters can be adjusted using either the *Property Pages*, the *Property List* or *VBA Code*.

Except for some special settings (which are available in the property list or via code only) TEC-IT recommends the use of the property pages. The property pages are designed for easy adjustment of the **TBarCode** properties.

6.3.1 Property Pages




Figure 3: Property Pages (Microsoft Word)

Application	How to open the Property Pages
Word	<ul style="list-style-type: none"> Make sure that you are in <i>Design Mode</i> (see section 6.2). Right-click on the TBarCode object ①. Select TBarCode8 Object ► Properties from the pop-up menu (②). The property pages ③ will appear.
Excel	
Access	
InfoPath	<ul style="list-style-type: none"> Make sure that you are in <i>Design Mode</i>. Right-click on the TBarCode object and select TBarCode8 Properties...

- For detailed information about the property pages and about the available settings, please refer to chapter 11.

6.3.2 Property List




Figure 4: Property List (Microsoft Word)

Application	How to open the Property List
Word	<ul style="list-style-type: none"> Make sure that you are in <i>Design Mode</i> (see section 6.2). Right-click on the TBarCode object ① and select Properties ② from the pop-up menu. <p>As an alternative you can also select the barcode and click on the Properties icon ③ in the <i>Control Toolbox</i>.</p> <ul style="list-style-type: none"> The property pages ④ will appear.
Excel	
Access	
InfoPath	No property list available.

- Some properties – in particular data binding (“*Linked Cell*” in Excel or “*Control Source*” in Access) – are available in the property list only. For more information on data binding, please refer to section 7.3.

6.3.3 Adjust Parameters per Code

Using VBA (Visual Basic for Applications) you can adjust the barcode parameters per code. For more information, please refer to section 8.4.

7 Set Barcode Data (Data Binding)

7.1 General


The barcode data can be provided in three ways:

- Manually
- Via Data Binding
- Via VBA (Visual Basic for Applications)

7.2 Specify Data Manually


You can specify the barcode data in the property pages or the property list:

7.2.1 Property Pages



- Open the property pages (see section 6.3.1).
- Select the “Barcode” tab.
- Enter the desired text in ❶.

7.2.2 Property List



- Open the property list (see section 6.3.2).
- Select the *Text* property.
- Enter the desired text in ❷.

7.3 Data Binding

Some Microsoft Office applications provide the option to bind the content of a specified data field to the **TBarCode** control (“data binding”). This means that the barcode control will use the content of the data field as barcode data. Whenever you change the content of the data field the barcode symbol will be updated as well.

Application	Data Binding
Word	Not available.
Excel	See section 7.3.1.
Access	See section 7.3.2.
InfoPath	See sections 10.3 to 10.5.

7.3.1 Microsoft Excel

Data binding can be enabled via the property *LinkedCell*:

- Make sure that you are in *Design Mode* (see section 6.2).
- Select the **TBarCode** object ❶.
- Then click on the *Properties* icon ❷ in the *Control Toolbox*.
(If you have inserted the barcode using the *Control Toolbox* (see section 5.3) you can alternatively right-click on the **TBarCode** object ❶ and select *Properties* from the pop-up menu.)
- The property list ❸ will appear.
- Select the property *LinkedCell* and as value enter the name of the cell that you want to bind to the **TBarCode** control (see ❹). In this sample B7 is used.




Figure 5: Data Binding in Microsoft Excel

7.3.2 Microsoft Access

The barcode control can be used in reports and forms. Most commonly the barcode is bound to a table column. If this is done, the barcode changes according to the data record which is currently being displayed.

In order to bind the barcode to a data source, please execute the following steps:

- Right-click on the **TBarCode** object ❶.
- Select *Properties* from the pop-up menu ❷.
- Select the *Data* tab ❸.
- For the property *Control Source* select the data field (or the query) that serves as source for the barcode content (see ❹).
This step is only possible if you have previously defined a data-source for the report/form.
You can do this by opening the properties dialog for the entire report.




Figure 6: Data Binding in Microsoft Access

- ▶ Please ensure that the barcode type corresponds with the data that you want to encode. If the source string contains characters which cannot be encoded with the selected symbology, an error message will be displayed instead of the barcode.
- ▶ Hint: You can also enter a fixed value or an expression as data source.
Example: The expression "[ArticleNo]+[Price]" could be used for concatenating the data fields *ArticleNo* and *Price* for the *EAN13 P5*.

7.3.3 Specify Data via VBA Code

Using VBA (Visual Basic for Applications) you can specify the barcode data per code. For more information, please refer to section 8.4.

8 Programming TBarCode (VBA)

8.1 General

TBarCode can be used in Microsoft Office and all other applications (e.g. development environments) which support ActiveX controls. The **TBarCode** object can be inserted as part of any form, document, report or spreadsheet, or it can be created as (invisible) instance which is used for printing only.

This chapter gives basic introductions on how to use the **TBarCode OCX** with VBA. For additional information and sample applications check out Appendix A.


8.2 Microsoft Office and VBA

In Microsoft Office all barcode properties (barcode type, barcode data, barcode size, etc.) and methods can be accessed directly via VBA code.

Basically, **TBarCode** can be inserted in two different ways:

- As *OLE Object*
- As *OLE Control*

Inserting **TBarCode** as *OLE Control* guarantees that the barcode object provides all properties (e.g. a name for identification) and interfaces which are necessary for programming. To make sure that the barcode is inserted as OLE Control you should insert the barcode via the *Control Toolbox* (see section 5.3).



Upon insertion the **TBarCode** control is usually named "TBarCode8n" (where *n* is a consecutive number). This name can be used for addressing the **TBarCode** control in the VBA code.

You can view (and also edit) this name by right-clicking on the respective barcode symbol. Then select *Properties...* from the pop-up menu. The name of the control is shown in ❶.

- To edit and to program the **TBarCode** control the design mode is required. For accessing the control in your VBA code use the name as assigned in ❶.

- Hint: If you double-click the control in design mode the VBA editor is opened (not shown).

- For a list of available properties and methods and for a detailed description of the **TBarCode** programming interface, please refer to the developer documentation (see Appendix A).

8.3 Insert Barcode

The following code samples can be used to create and to insert a barcode object in Office applications. You can execute the code with a macro or you can trigger it with a control event (e.g. button-click).

Application	How to Insert Barcode
Word	See section 8.3.1.
Excel	See section 8.3.2.
Access	No example available.
InfoPath	No VBA supported.

8.3.1 Microsoft Word

This sample shows how to insert a Code-128 symbol at the actual cursor position. The barcode data will be set to "1234567890".

```
Dim oShape As InlineShape
Dim oTBC As Object

' Insert a shape containing a barcode object at the actual cursor position.
Set oShape = Selection.InlineShapes.AddOLEObject(ClassType:="TBarCode8.TBarCode8.1", _
    FileName:="", LinkToFile:=False, DisplayAsIcon:=False)

' Activate the barcode object.
oShape.OLEFormat.Activate

' Adjust the size of the barcode by adjusting the shape.
' (The barcode object extends to the size of the shape by default).
oShape.Width = 200
oShape.Height = 100

' Get the barcode object within the shape.
Set oTBC = oShape.OLEFormat.Object

' Adjust the barcode object properties (barcode type, barcode data...)
oTBC.BarCode = 20 ' select Code-128 (TBarCode8Lib.eBC Code128)
oTBC.Text = "1234567890" ' set barcode data
```

► This samples inserts **TBarCode** as *OLE Object*. To insert the barcode as *OLE Control* you have to use the command **AddOLEControl**.

8.3.2 Microsoft Excel

This sample shows how to insert a Code-128 symbol in cell "C3" on the current spreadsheet. The barcode data will be set to "123456" and the size of the human readable text to 8 points.

```
Dim TargetCell As Variant ' The cell, in which you want to insert the barcode
Dim CellHeight As Variant ' Height of the target cell
Dim CellWidth As Variant ' Width of the target cell
Dim CellTop As Variant ' Top coordinates of the target cell
Dim CellLeft As Variant ' Left coordinates of the target cell
Dim BCObject As OLEObject ' The TBarCode container object

TargetCell = "C3"

' Make sure that the cell height has 30 pixels minimum
If (Range(TargetCell).RowHeight < 30) Then
    Range(TargetCell).RowHeight = 30
End If

' Get target cell dimensions
CellHeight = Range(TargetCell).Height
CellWidth = Range(TargetCell).Width
CellTop = Range(TargetCell).Top
CellLeft = Range(TargetCell).Left

' Insert barcode object into selected cell
Set BCObject = ActiveSheet.OLEObjects.Add(ClassType:="TBarCode8.TBarCode8.1",
    Left:=CellLeft,
    Top:=CellTop,
    Width:=CellWidth,
    Height:=CellHeight)
```

```
' Adjust the barcode object properties (barcode type, barcode data...)
BCObject.Object.BarCode = 20      ' select Code-128 (TBarCode8Lib.eBC Code128)
BCObject.Object.Text = "123456"    ' set barcode data
BCObject.Object.FontSize = 8      ' set size of human readable text
```

► Via VBA code the barcode can only be inserted as *OLE Object* (not as *OLE Control*).

8.4 Adjust Barcode Parameters and Barcode Data

Application	How to Adjust Barcode Parameters
Word	See section 8.4.1.
Excel	
Access	See section 8.4.2.
InfoPath	No VBA supported.

8.4.1 Microsoft Word or Excel

The example below shows basic **TBarCode** method calls. The barcode object is identified by the name "TBarCode81" (see section 8.2).

```
TBarCode81.BarCode = TBarCode8Lib.eBC DataMatrix ' select the barcode type DataMatrix
TBarCode81.Text = "Hello World!"                ' set the barcode data
```

8.4.2 Microsoft Access

► To access the barcode properties and methods you have to use the *"object"* interface.

The example below sets the barcode data (text property) of **TBarCode**. The barcode object is identified by the name "TBarCode81" (see section 8.2)

```
TBarCode81.Object.Text = "1234567890" ' set the barcode data
```

8.5 License TBarCode

Call the method *LicenseMe()* from within your application. Do this before barcodes are generated or printed. Before calling this function the TBarCode OCX control must be instantiated, otherwise an error message will be received.

To license **TBarCode** use the following VBA call:

```
TBarCode81.LicenseMe "Licensee", eLicKindDeveloper, 1, "LicenseKey", eLicProd1D
```

9 The TBarCode Office Add-In

9.1 General

The **TBarCode** Office Add-In (which is part of the *TBarCode8* Setup) adds the following toolbar in Microsoft Word:



Figure 7: TBarCode Toolbar


This toolbar makes it easy to access the most important functions of the **TBarCode OCX** control without the need to navigate through any menus:

Button	Description
New Barcode	Inserts a new barcode symbol at the actual cursor position and opens the property pages for the new barcode. If the user selected some text before clicking this button, the barcode content is set to this text. (For a description on how to insert a barcode symbol without the use of the toolbar, please refer to section 5).
Properties	Opens the property pages for the selected barcode. (For a description on how to open the property pages without the use of the toolbar, please refer to section 6.3.1). A detailed description of the property pages can be found in chapter 11.
Serial Letter	Replaces text sections that are located between a pattern prefix and a pattern postfix by barcodes. The text between prefix and postfix becomes the content of an inserted barcode.
Help	Opens this user manual.
License	Opens the license dialog. For more information on licensing TBarCode, please refer to chapter 12.
About	Displays the product and version info for TBarCode.

Table 1: TBarCode Toolbar Description

- ▶ Please note: The toolbar is available for Microsoft Word 2000 or newer versions only!
- ▶ If the toolbar is not visible after installation, please close all instances of Word and Outlook (Word may be used as e-mail editor), and then start Word again!

9.2 Insert Barcode using the TBarCode Toolbar



Click on icon ❶ to insert the **TBarCode OCX** control at the current cursor position (❷). (The barcode is inserted as *OLE Control*.)

Please Note:
When inserting the first barcode (after Word was started) the document will switch to *Design Mode* (see ❸) automatically!

After the barcode is inserted, the property pages open to allow the user to change the barcode settings immediately. If the user selects a text passage before clicking *New Barcode*, the selected text is passed to the barcode content.

9.3 Adjust Barcode Parameters using the Toolbar

Click on the *Properties* button  to open the property pages.

► This button can also be used if the *Design Mode* (see section 9.2, ) is de-activated.

9.4 Serial Letter Command




Figure 8: The Serial Letter Dialog

In order to start the serial letter function execute following steps:

- Click on the button *Serial Letter* ①.
- Change the *Search Pattern* according to your needs ②.
The first edit box contains the prefix, the second edit box the postfix (here "<" and ">"). If a text section is found that matches this pattern, it is replaced by a barcode and the replaced data is passed to the barcode content.
- If you choose to check the *Include Pattern into Barcode Data* check box, the barcodes will contain not only the text between prefix and postfix but also the pattern itself.
- Optionally you can change the size of the inserted barcodes (*Width* and *Height*) or the barcode specific properties by clicking *Edit Properties...* ③.
- At last confirm your edits by clicking *OK* ④.




Figure 9: Result of the Serial Letter Function

After pressing ok the result may look as in *Figure 9: Result of the Serial Letter Function*.

10 Barcodes in Microsoft InfoPath®


10.1 General

In order to use **TBarCode** in Microsoft InfoPath you have to perform the following steps:

- Open your form in *Design Mode* (see section 10.2).
- Add **TBarCode** to the *Custom Controls* (see section 0). This step is required only once. It enables Microsoft InfoPath to use **TBarCode**.
During this step you have to specify the data source type for **TBarCode**. You have to decide whether you want to encode:
 - the content of single data fields or
 - the underlying InfoPath XML document (or parts of the XML document).
- Insert the barcode (see section 10.4).
- Change the data binding (optional) – see section 10.5.
- Adjust barcode parameters (see section 10.6).

10.2 Activate the Design Mode

Please note: you have to be in *Design Mode* to add barcodes to a form design, to select, move, resize and to adjust the barcode parameters.



You can activate the *Design Mode* by clicking on the triangle symbol  in the *Standard* toolbar. – The design view will be opened in a separate window.

Location

10.3 Add TBarCode to the Custom Controls

To add **TBarCode** to the *Custom Controls*, please follow the steps below:

- Make sure that you are in *Design Mode* (see 10.2).
- Open the *Task Pane* ❷. Therefore select **View ► Task Pane** from the menu (see ❶).




Figure 10: Add TBarCode to the Custom Controls in Microsoft InfoPath (1)

- In the *Task Pane* click on **Controls** ❸.
- Then click on **Add or Remove Custom Controls...** at the bottom of the updated pane view (see ❹). A dialog will appear. This dialog shows a list of installed custom controls.
- Click the **Add...** button ❺ to open the “Add Custom Control Wizard”.
- Locate and select **TBarCode8** in list ❻, then click **Next**.
- On the following wizard pages you have to specify the data source type for **TBarCode**. This selection determines, how the barcode control can be used in InfoPath later on. For more information, please see below.




Figure 11: Add TBarCode to the Custom Controls in Microsoft InfoPath (2)


10.3.1 Specify Data Source Type

In the “Add Custom Control Wizard” you have to decide which kind of data you want to encode:


- If you plan to encode single data fields (e.g. the content of an input box), please follow the instructions in section 10.3.1.1.
- If you plan to encode the underlying InfoPath XML document (or parts of the XML document), please follow the instructions in section 10.3.1.2.

10.3.1.1 Encode Single Data Fields

Perform these steps if you plan to encode single data fields:




- Select the binding property **Text** (see ①).
- Click **Next**.
- On the next page ("Specify and Enable or Disable Property") select the entry **Enabled**.
- Click **Next**.




- In ② select "Field (element or attribute)".
- Then select all data types (by clicking each single line in ③).
- Leave the default data type ④ as "Text (string)".
- Then click **Finish**.

10.3.1.2 Encode Complete or Partial Form Content (XML Data)

Perform these steps if you plan to encode XML data:



- Select the binding property **Value** (see ①).
- Click **Next**.
- On the next page ("Specify and Enable or Disable Property") select the entry **Enabled**.
- Click **Next**.



- In ② select “Field or Group (any data type)”.
- Then click *Finish*.

10.3.2 Finish Adding the Custom Control

- After you have completed the wizard, the **TBarCode** control will be listed in ⑦.
- Click **OK** (⑧).
- **TBarCode8** appears in the list of available controls (⑨).




Figure 12: Add TBarCode to the Custom Controls in Microsoft InfoPath (3)

10.4 Insert Barcode

After you added **TBarCode OCX** to the *Custom Controls* in Microsoft InfoPath (see section 10.4) you can add a barcode to your document by performing the following steps:

- Place the cursor where you want to insert the barcode and click on the **TBarCode** control in the *Task Pane* (1).
- Before the barcode is actually inserted a dialog named “*TBarCode8 Binding*” appears.
- Select the required field (📄) or group (📁) as data source (see 2). The content of the selected entry will be encoded as barcode.

► Please note:
If you have selected single data fields as data source type (see 10.3.1.1) you can select fields only (no groups!).

- Press **OK**. A new barcode object will be inserted.





Figure 13: Insert TBarCode in a Microsoft InfoPath Document

10.5 Change Binding



To change the binding which was specified upon insertion of **TBarCode** (see Figure 13, ❷), right-click on the barcode and select **Change Binding...** from the pop-up menu. The “*TBarCode8 Binding*” dialog appears.

Select a field (or group) from the tree view and confirm with **OK**.

10.6 Adjust Barcode Parameters

The barcode parameters can be adjusted using the *Property Pages* (a *Property List* is not available). Please open the property pages as follows:

- Right-click on the barcode object ❶.
- Select **TBarCode8 Properties...** from the pop-up menu (❷).
- The property pages ❸ will appear.

► For detailed information about the property pages and about the available settings, please refer to chapter 11.




Figure 14: Adjust Barcode Properties in Microsoft InfoPath

10.7 Multiple Barcodes

The feature “Multiple Barcodes” (which is available since **TBarCode OCX 7.0**) was designed especially for Microsoft InfoPath. It allows you to encode the contents of an InfoPath form into multiple barcodes. Therefore the control becomes suitable even for large amounts of data!

The screenshot shows the Microsoft Office InfoPath 2003 application window titled 'Preview5 - Microsoft Office InfoPath 2003'. The form is titled 'Service Request' and contains the following fields:

- Request Number:** 0012095008
- Date:** 27.09.2006
- Contact Information:**
 - Requested By:** John Smith
 - Phone Number:** (555)768093
 - E-mail Address:** John.Doe@mail.net
- Location:**
 - Office Location:** Right Here
 - Space:** (empty field)
- Service:** Choose a service type... (dropdown menu)
- Problem:** Choose a problem type... (dropdown menu)
- Description:** (empty text area)

Below the form fields, there are three square barcodes generated from the form data. The status bar at the bottom indicates the form template's location: C:\Documents and Settings\stephang\Local Settings\Application Data\Microsoft\InfoPath\...

Figure 15: Multiple Barcodes in Microsoft InfoPath

Please, consider the following points when using multiple barcodes in InfoPath:

- Select a suitable barcode type (symbology) and enable the generation of multiple barcodes. For detailed information on multiple barcode adjustments, please refer to section 11.4.
- For encoding the content of the whole document (XML data) use the settings as described in section 10.3.1.2.
- For reducing the amount of data (when encoding the whole document, e.g.) enabling data “*Compression*” is recommended (see section 11.2.8).

11 The Property Pages

11.1 Introduction

The property pages of **TBarCode** (and all settings which can be adjusted within the property pages) are described in detail below. See section 6.3.1 on how to open the property pages.

11.2 Property Page “Barcode”

The first property page is the “Barcode” tab. It contains basic barcode adjustments like Barcode Type (Symbology), Barcode Data, etc. For most applications adjusting these settings will be sufficient. Additional parameters can be changed on demand (button “Adjust...”, tabs “Appearance”, “Multiple Barcodes”, “Font” and “Color”).




Figure 16: Property Page “Barcode”

11.2.1 Barcode Type (Symbology)

Select the barcode type that you want to create. Common linear barcode types are UPC (USA), EAN (Europe), Code 128, Code 39, 2 of 5 Interleaved. Common 2D barcode types are Data Matrix and PDF417.

For information on the different barcode types (symbologies), please refer to the Barcode Reference (see Appendix A).

11.2.2 Button “Adjust...”

The *Adjust...* button will open a barcode specific properties dialog (for the selected barcode type / symbology). This button is available for 2D barcodes and for composite symbologies only!

Barcode specific settings are described in sections 11.7 to 11.14.

11.2.3 Barcode Data

The content of this textbox will be encoded as barcode. Depending on the selected barcode type you can encode different kinds of data:

- Some barcodes can be used to encode digits only.
- Others allow the usage of digits and a limited number of special characters like "/" or "*".
- Again, others can be used to encode arbitrary alphanumeric data.

For more information on barcode types and on encodable data, please refer to the Barcode Reference (see Appendix A). Below *BarCode Data* the number of letters that the data currently contains.

- ▶ If the "Barcode Data" can not be represented with the selected symbology, a big "X" is drawn instead of the barcode. Additionally an error code and a short error description are displayed.

11.2.4 Encoding Mode

The Encoding Mode specifies how the input data should be interpreted.

- ▶ Data is always passed as UNICODE stream to **TBarCode OCX**. As UNICODE characters always consist of 2 bytes and most of the barcode types are only able to encode one byte per character, it is not always clear how the input data should be interpreted. So we give you the possibility to decide yourself.
- ▶ Per default the input data is converted to the selected *Code Page* (see below). If other kinds of interpretations are needed, you have to change this property.

You have following possibilities:

Value	Description
Convert to Code Page	Converts the input data to the code page, which is selected in the property <i>Code Page</i> . (default)
No conversion (Lower bytes only)	Considers only the lower bytes of the input characters, the higher bytes are ignored.
Bytestream (Lower before higher byte)	The data is passed as it is. No conversion is done. Both bytes are considered. The lower byte is passed before the higher byte.
Bytestream Reverse (Higher before lower byte)	Consider both bytes but change the order of lower and higher byte. That means the higher byte is encoded before the lower byte.

Table 2: Compression

11.2.5 Code page

The code page is related to the property *Encoding Mode*. It is only considered if the encoding mode is set to *Convert to Code Page*. You can choose between several pre-defined code pages (e.g. ANSI, ISO 8559-1 Latin I, UTF-8, Shift-JIS...) or add the ID of a custom code page.

11.2.6 Format/Subset

The format string is used for formatting the utilizable data of the barcode prior to encoding it.

The format string is built upon placeholders, which can be combined with constant data characters to build the final data string. Certain control characters make it possible to change the Subsets for Code 128, EAN 128 and UCC 128 or to define the desired start/stop character of CODABAR.

For detailed information on format strings, please refer to the Barcode Reference (see Appendix A).

11.2.7 Check Digit

Here you can change the calculation method of the check digit. Whether you need a check digit or not depends on your application and on the selected barcode type.

By default the appropriate check digit is selected automatically (entry *“Default”*), which means that the check digit is calculated according to the barcode specification. Any other suitable calculation method can be selected via the combo box.

Why check digits? In order to guarantee that the barcode data is read properly, a check digit is inserted (usually) at the end of the utilizable data. A comparison of the barcode content and the check digit informs the scanning device about the correctness of the scan. It causes the device to accept or to reject (repeat) the scan. The check digit calculation method is standardized for certain common barcodes.

- ▶ A change of the check digit method is admissible for special applications or for barcodes with selectable check digit methods only.
- ▶ For some barcodes the standard is no check digit. However, using a check digit is recommended (e.g. LOGMARS or Code39). You can use the combo box for enabling check digit calculation.

11.2.7.1 Check Digit Override

Some barcodes with a predefined number of utilizable data characters (like all EAN, UPC, Postnet and RSS-14 codes) include a check digit on a fixed position in the barcode data.

Example:



The EAN13 code permits 12 utilizable digits plus 1 check digit at the last position (❶).

If you enter 12 digits as barcode data this last digit (the check digit) will be calculated and inserted automatically. However, you can also enter all 13 digits and therefore override the calculated check digit.

- ▶ Note: If the check digit is supplied within the barcode data, the internal check digit calculation will be switched off.
- ▶ **TBarCode** does *not* check the correctness of the check digit supplied by your application.

“Check digit override” was primarily designed for use with article databases, in which the check digit is already included in the article numbers. However, the check digit override can also be used to calculate and to provide your own check digits (usually by program code) or to use all possible digits for utilizable data (in non standard applications).

Under normal circumstances you should not use this feature – we recommend the automatic calculation of check digits by **TBarCode**.

11.2.8 Compression

To increment the capacity of barcodes you can compress the *“Barcode Data”*. This means that the data provided by the user will be compressed before it is encoded as barcode.

The compression is only available for barcodes which allow the encoding of arbitrary binary data and a variable length of input data. By default the compression is set to *“None”*.

Value	Description
-------	-------------

None	The barcode data will not be compressed. It will be stored in the barcode as is (default).
Deflate (RFC 1951)	The barcode data will be compressed using the Deflate algorithm. We recommend using this algorithm if data compression is required.
GZip (RFC 1952)	The barcode data will be compressed using the GNU zip algorithm.
ZLib (RFC 1950)	The barcode data will be compressed using the ZLib algorithm.

Table 3: Compression

- Note: When reading compressed barcode data, you will have to decompress it in order to restore the original input data. Decompression can be done through the **TBarCode InForm** software decoder (which restores the uncompressed data automatically). – Or you can use any third party software library for decompression.

11.2.9 Suppress Error Messages

If the barcode data contains invalid characters (e.g. letters for code 2 of 5 Interleaved), or if the wrong number of input characters is provided, an error message is displayed (instead of the barcode).

If “*Suppress error message*” is enabled, this error message will be suppressed. Only blank space is displayed instead of any error information.

11.2.10 Translate Escape Sequences

Selects whether escape sequences (like \n) are translated or not (default: no).

The use of escape sequences is useful if you need to encode control characters such as Carriage Return or FNC1. For encoding binary data (e.g. Data Matrix) this feature may be very useful as well.

For more information on escape sequences, please refer to the Barcode Reference (see Appendix A).

11.2.11 Button “License...”

Opens the license dialog. For more information on how to license the product, please refer to chapter 12.

11.2.12 Button “About...”

Opens the about dialog. The about dialog shows the product version and copyright information.

11.3 Property Page “Appearance”




Figure 17: Property Page “Appearance”

11.3.1 General

11.3.1.1 Orientation

Specifies the orientation of the barcode. Selectable values are 0°, 90°, 180° and 270°. The barcode is rotated counter-clockwise.

- Please note: Some fonts (for the human readable text) do not support rotation (e.g. some bitmap fonts). If rotation is required we recommend selecting a TrueType® font.

11.3.1.2 Print Ratio

The print ratio is the relationship between the bar-widths and the space-widths of a barcode. Another term for print ratio is “bar width ratio” or “bar/space width ratio”.

- By default there is no need to change the print ratio, unless needed for any special application. – Please consider: Barcodes may become unreadable when manipulating this value!

The print ratio must be specified in a specific format. This format depends on the number of different bar- and space-widths used in the selected symbology.

Example: If a barcode element has 4 different bar widths and 4 different space widths, the print ratio looks like this (Code 128): 1:2:3:4:1:2:3:4. In the first part (“1:2:3:4”) the width ratio of the bars is set, in the second part the relation of the spaces is set (in our case, they are the same). The smallest bar is “1” wide, the next larger is “2” wide (thus twice as wide as the smaller bar) and so on.

For more information on print ratios, please refer to the Barcode Reference (see Appendix A).

11.3.1.3 Back Style

The barcode can be painted with transparent background (default, background shines through) or with opaque background (background is drawn in the adjusted color).

- If the back style is set to “*Transparent*”, the adjusted background-color will be ignored.

11.3.1.4 Notch Height [1/1000 mm]

Sets the notch height in 1/1000 mm.

Certain barcode types need use guard bars or synchronization bars. These bars are longer than the others. The part of the longer bars that sticks out is among the others is called *notch*. The Property *Notch Height* defines the length of the notches. Guard bars are used for instance for EAN-8, EAN-13, UPC-A, etc.

11.3.1.5 Bearer Bars

Usually, bearer bars are used with the ITF-14 (or sometimes with the Interleaved 2 of 5) or the DPD symbology only. The bearer bars were introduced to equalize the pressure exerted by the printing plate over the entire surface of soft materials. They also enhance the reading reliability by helping to reduce the probability of misreads by skewed scanning beams.

For some types (like UPC and EAN) the bearer bars must be set to “*None*”.

Value	Description
None	Do not print bearer bars.
Top and Bottom	Print bearer bars at the top and the bottom of the symbol.
Rectangle	Print bearer bars on all 4 sides of the symbol. For rectangular bearer bars, the quiet zone (see section 11.3.1.7) must be at least 12 times the module width. Otherwise no bearer bars will be printed.
Top	Print bearer bars at the top of the symbol.
Bottom	Print bearer bars at the bottom of the symbol.

Table 4: Bearer Bars

11.3.1.6 Bearer Bar Width [1/1000 mm]

Sets the width of the bearer bars in 1/1000 mm.

- The minimum width of the bearer bars is two times the module width (which is also used as default value). If any smaller value is entered, the minimum width will be used instead.

Note: If the bearer bar width is set to zero, no bearer bars are printed.

11.3.1.7 Draw Mode

Due to problems with certain printer drivers, **TBarCode** is able to use different methods to draw barcodes. You can choose between following modes:

Value	Description
Default / Quality	Print the bars in best quality, but may not be supported on by all applications or printers.
Performance	Print the bars in best performance, with a little reduction of quality, but will work on nearly all systems.
Combo	Combines both draw modes. Should work nearly everywhere.

11.3.1.8 Quiet Zone [modules]

This setting is currently supported for 1D barcodes and for Data Matrix only. For most 1D barcodes a quiet zone (= an empty area) should be maintained directly before and after the barcode symbol. The quiet zone helps the scanner to read the barcode correctly. As a rule of thumb, the quiet zone should be ten times the dimension of the module width or at least 1/4 inch (6.5 mm). The exact value depends on the selected barcode type.

- ▶ Regardless of this setting a few barcode types provide the required quiet zone automatically. These barcodes are: EAN-8, EAN-13, UPC-A, Telepen Alpha, PDF417, MicroPDF417 and all composite barcodes. Changing the quiet zone for these symbologies will add an additional space (1D barcodes) or it will leave the barcode symbol unchanged (2D barcodes).

Default: No additional quiet zone is added.

11.3.2 Text Options

The text options allow the adjustment of the human readable text. The human readable text is usually printed below the barcode symbol and shows the content of the barcode.

- ▶ Not all barcode specifications support the printing of human readable text. If human readable text is not supported, the following setting will be ignored.

11.3.2.1 Print Text

Specifies whether the barcode data is printed as human readable text or not. Default: Yes.

11.3.2.2 Above Symbol

Prints the human readable text above the symbol (default: below).

- ▶ For some barcodes, like UPC and EAN, the adjustment "Above symbol" is not permitted.

11.3.2.3 Alignment

Changes the alignment of the human readable text.

Value	Description
Default	Uses the default text alignment (= "Center").
Left	Aligns the human readable text to the left.
Right	Aligns the human readable text to the right.
Center	Centers the human readable text.

Table 5: Text Alignment

11.3.2.4 Text Distance

Allows you to specify the distance between the human readable text and the barcode (in 1/1000 mm). If "Default" is marked, the minimum text distance is used. Otherwise the given value will be added.

11.3.3 Barcode Size and Module Width

11.3.3.1 Mode

This option selects the calculation method for the barcode size.

Value	Description
Default - Fit to bounding rectangle	Draws the biggest possible barcode which fits into the bounding rectangle. Resizing the bounding rectangle directly resizes the barcode.
Custom - Specify module width	Uses the specified module width for drawing the barcode (see section 11.3.3.2).
Minimal - Optimize for readability	Creates the smallest possible barcode for the selected "Resolution" (see section 11.3.3.3) and for the selected "Decoder" type (see section 11.3.3.5). Furthermore the module width of the barcode will be optimized for ensuring best readability.

Table 6: Size Mode

- Please note: The size modes "*Custom*" and "*Minimal*" influence the horizontal(!) size of a barcode only! The barcode height is always given by the height of its bounding rectangle. Only a few 2D barcodes, like Data Matrix, QR-Code or Composite symbologies require a fixed width to height ratio. For these barcodes the height will be calculated accordingly.

11.3.3.2 Module Width [1/1000 mm]

If the size mode is set to "*Custom – Specify module width*", this input box lets you specify the size of one module (in 1/1000 mm).

A module is the smallest element of a barcode. The widths of all bars and spaces are multiples of one module width.

Sometimes the "*Module Width*" is also called "*Narrow Bar Width*".

A constant module width is recommended if you have a varying amount of input data and if the optical data density should remain constant. Furthermore, some label specifications require a constant module width.

- Please note: When specifying a custom module width the barcode may grow bigger than the bounding rectangle for big module widths or for a large amount of input data. Please make sure that the bounding rectangle is wide enough to display the whole barcode symbol. To ensure that no regions of the barcode are clipped, you can enable the option "*Display error if barcode is clipped*" (see section 11.3.4).

11.3.3.3 Resolution

The size mode "*Minimal - Optimize for readability*" requires the "*Resolution*" of the printer/scanner to be selected: As value select the lowest resolution, which is used within the chain of barcode processing (printing, scanning). Additionally you have to select the decoding solution from the "*Decoder*" combo box below. So it can be guaranteed that the printed barcode will be readable for the selected configuration.

Examples:

- If the barcode is printed with 600 dpi and then scanned with a hardware scanner, the resolution should be set to "*600 dpi (Good print quality)*". As decoder select "*Hardware*".
- If the barcode is printed with 600 dpi, transmitted with a fax device (200 dpi) and then scanned with a hardware scanner, the resolution should be set to "*200 dpi (Fax)*". As decoder select "*Hardware*".
- If the barcode is printed with a laser printer (600 dpi) and if it is then scanned with a flat bed scanner (150 dpi) and then decoded via software you should select a custom resolution of "*150 dpi*". As "decoder" select "*Software*".

Value	Description
96 dpi (Screen)	Specifies the default screen resolution.
200 dpi (Fax)	Specifies the default fax resolution.

202 dpi (Thermo transfer)	This resolution is used by thermo transfer printers (e.g. by Zebra® printers).
300 dpi (Poor print quality)	Specifies a low printer resolution.
600 dpi (Good print quality)	Specifies the standard printer resolution.
Custom dpi	Specifies any other resolution. The dpi value can be entered in the input box on the right (see section 11.3.3.4).

Table 7: Resolution

11.3.3.4 Custom Resolution (DPI)

Specifies the custom dpi value for the size mode “*Minimal - Optimize for readability*” if Resolution is set to “*Custom dpi*”.

11.3.3.5 Decoder

Specifies, which kind of decoder is used for reading the barcode content (size mode “*Minimal - Optimize for readability*”).

Value	Description
Both Hardware and Software	Select this option if you do not know which type of barcode decoder will be used. Based on the adjusted resolution (see section 11.3.3.4), TBarCode OCX will automatically choose a barcode size which can be read with both decoder types, Software and Hardware. ► If you are unsure about the resolution, we recommend a setting of 200 dpi (?). This should be readable in most cases.
Hardware	Select this option if the barcode is scanned (and decoded) via a scanning device (e.g. handheld scanner). This setting guarantees a minimal module width of 0.254 mm for linear barcodes and 0.5 mm for 2D barcodes. These values are recommended for most hardware scanners.
Software	Select this option if the barcode symbol is received as an image (e.g. via flat bed scanner, camera, fax software, etc.) and decoded via software solution. This setting guarantees a minimal module width of 5 pixels. This value ensures readability by most software decoders.
TBarCode InForm	Select this option if you plan to use the (upcoming) TBarCode software solution for decoding the barcode symbol.

Table 8: Decoder

11.3.4 Display Error if Barcode is Clipped

For certain configurations, it is possible that the barcode grows bigger than the bounding rectangle. In this case all bars which extend the size of the bounding rectangle are clipped by default.

To make sure that the barcode does not remain unreadable (because of clipped regions), you can check the option “*Display error if barcode is clipped*”. If this property is set, and if the barcode extends the size of the bounding rectangle, no barcode will be drawn at all. Instead an error is displayed.

This option may help you to avoid truncated barcodes; incorrect printouts can be detected immediately.

11.4 Property Page “Multiple Barcodes”




Figure 18: Property Page “Multiple Barcodes”

11.4.1 Enable Multiple Barcodes

This option enables the generation of multiple barcodes.

Multiple barcodes can be used for encoding large quantities of data. The data will be split up and encoded into multiple barcode symbols automatically.

Multiple barcodes are supported for the following symbologies:

- Aztec Code
- Data Matrix
- MicroPDF417
- PDF417
- PDF417 Truncated
- QR-Code

11.4.2 Number of Barcodes

Specifies the number of barcodes to be created (rows and columns).

Basically, the partitioning of the input data depends on various factors: amount of data, selected symbology, size of the bounding rectangle, size mode, etc. **TBarCode** always tries to pack as much data as possible into one symbol. As a consequence the number of resulting barcodes will be minimized.

Multiple symbols will only be created, ...

- if the horizontal or vertical size of one barcode symbol exceeds the size of the bounding rectangle or of one row/column (see below).
- if the data limit of one barcode is reached (barcode specification or manual limitation, see section 11.4.4).

Specifying the number of rows/columns internally divides the bounding rectangle evenly into multiple “cells”, which are reserved for one barcode each.

The dimensions of one cell are calculated based on the given number of rows/columns and on the

“Minimum barcode distance” (see section 11.4.3). With an increasing amount of input data an increasing number of cells is filled with barcode symbols.

Value	Description
Cols="Auto" Rows="Auto"	Tries to use the available space (bounding rectangle) as good as possible. (Little amount of barcode symbols with lots of data each.)
Cols=X Rows=Y	Divides the bounding rectangle into X*Y cells. Depending on the amount of input data one ore more cells are populated with barcode symbols. The number of barcode symbols is restricted to X*Y.
Cols=X Rows="Auto"	Divides the bounding rectangle into X columns. The number of columns is fixed (X). The number of rows may vary, but is limited by the height of the bounding rectangle.
Cols="Auto" Rows=Y	Divides the bounding rectangle into Y rows. The number of rows is fixed (Y). The number of columns may vary, but is limited by the width of the bounding rectangle.

Table 9: Number of Barcodes

11.4.3 Minimum Barcode Distance [1/1000 mm]

This option lets you specify the minimum (horizontal and vertical) distance between the single barcode symbols. If “Default” is selected, TBarCode will set this value automatically.

11.4.4 Data Limit per Barcode [Bytes]

By default, the largest possible amount of data is encoded per barcode. This amount is limited by the barcode specification and by the available space (bounding rectangle) only. Un-checking the “Default” checkbox you can limit the barcode data to a given number of bytes. As a consequence the data encoded in one single symbol will never grow bigger than specified.

This can be helpful for barcode scanners which have difficulties with very large barcodes.

11.4.5 Structured Append

If structured append is enabled, some additional header information (total number of barcodes, index, ...) will be included in each of the barcodes. This information is used for identifying the correct order, when re-joining the split-up input data.

Value	Description
None	Disables structured append (= no additional header information will be added). If the barcodes are scanned in the wrong order, the original data can not be restored correctly.
Standard	Uses the standard structured append method of the selected barcode type. This mode allows barcode scanners to append the data of multiple barcodes correctly, even if they are scanned in the wrong order. Note: Not all barcodes have a standard (native) structured append mode.
TBarCode InForm	Uses a custom structured append method: The header information is prepended to the “normal” barcode data. This method can be used if the selected barcode type or the decoder does not support standard structured append. For decoding TBarCode InForm or a custom software solution is required.

Table 10: Structured Append

11.4.6 Dynamic Bounding Rectangle

Specifies the behavior of the bounding rectangle.

By default the bounding rectangle limits the space which is available for drawing barcodes (*“Don’t grow”*). This means, if a barcode (or the sum of all barcodes) grows bigger than the bounding rectangle, an error message will be displayed.

By changing the value to *“Grow horizontally”* or to *“Grow vertically”* you can allow the bounding rectangle to grow dynamically with increasing amount of input data. This may be useful if the amount of input data can vary, and if the space which is reserved for barcodes is not limited.

- The features *“Grow horizontally”* and *“Grow vertically”* were originally implemented for Microsoft InfoPath. Other applications (e.g. Microsoft Access) do not necessarily support these features!

Value	Description
Don't grow	The size of the bounding rectangle is fixed (Default).
Grow horizontally	The bounding rectangle can grow horizontally. If the required space for the barcodes exceeds the size of the bounding rectangle, it will grow horizontally.
Grow vertically	The bounding rectangle can grow vertically. If the required space for the barcodes exceeds the size of the bounding rectangle, it will grow vertically.

Table 11: Dynamic Bounding Rectangle

11.5 Property Page “Font”

In this menu you can adjust the font for the “human readable text”.




Figure 19: Property Page “Font”

11.5.1 Properties

The entry “Font” is pre-selected.

11.5.2 Font

Selects the font type. The combo box lists all fonts which are available under your operating system.

► Please consider that some fonts can't be rotated. Therefore, if rotation is required we recommend selecting a TrueType® font.

11.5.3 Size

Specifies the font size in points.

11.5.4 Effects

Applies additional text effects. Please, check the corresponding option to create bold, italic, underlined and/or stroked-out text.

11.5.5 Sample Text

Shows a preview of the selected font.

11.6 Property Page “Color”

The colors of the barcode, of the human readable text and of the background can be set here.




Figure 20: Property Page “Color”

To change the color for one of the barcode components (background, foreground, human readable text), first select the corresponding property in ❶. Then click on the desired color in ❷.

► Please note: The color in ❶ will only be updated when switching between the list entries.

11.6.1 Properties

Select the property that you want to change:

- BackColor
The background color of the barcode (color of the spaces). If the back style is set to “Transparent”, the adjusted background-color will be ignored.
- ForeColor
The foreground color of the barcode (color of the bars).
- TextColor
The color of the human readable text.

11.6.2 Color Set

You can choose between “Standard Colors” and “Windows System Colors”. Each of these color sets offers a different color palette.

11.6.3 Color Palette

Clicking on one of the list entries assigns the color to the selected property.

11.6.4 Edit Custom Color...

Clicking this button opens a dialog which lets you select a color for the list entry <Custom...>. Alternatively you can also double-click on the <Custom...> list entry.

11.7 Adjust...

Depending on the selected barcode type **TBarCode** offers additional barcode specific adjustments. You can access these adjustments by clicking on the *Adjust...* button in the “Barcode” tab. This button is available for Aztec Code, Codablock-F, Data Matrix, MaxiCode, MikroPDF417, PDF417, PDF417 Truncated, QR-Code and all Composite Symbolologies.




Figure 21: Adjust...

The following sections 11.8 to 11.14 will give an overview over barcode specific properties.

- Please take care when modifying these properties. Some settings may result in unreadable barcodes. Always make a test scan in case of doubt!

11.8 Adjust Properties: Aztec Code

Aztec Code is a 2-dimensional Matrix Code. Characteristic for the Aztec Code is the finder in the center of the symbol which contains of 3 to 5 lapping squares.




Figure 22: Advanced Properties: Aztec Code

11.8.1 Format / format specifier

You can choose from:

Value	Description
Default	The standard format of Aztec Code.
UCC/EAN	Special format defined by UCC and EAN. Used for encoding so-called Application Identifiers. FNC1 is added at first position.
Industry	For special industry formats. If you choose this value, you have to fill in a Format Specifier (2 digits or 1 letter). It determines which industry format the barcode data corresponds to. FNC1 is inserted at second position.

11.8.2 Symbol Size

Defines the size of the Aztec Code symbol. Possible values range from "(1) 15 x 15" to "(33) 151 x 151" modules. If the property is set to default, the size is computed automatically based on the length of the barcode data.

Additionally you can select one of three reader mode: 19x19 reader, 23x23 reader, 27x27 reader. These modes are often used to program the barcode scanners.

11.8.3 Enforce binary encoding

If checked binary mode is used for encoding (no input data analysis). This mode is recommended if you want to encode binary input data.

► In version 8 of **TBarCode** only binary encoding is implemented and this property cannot be changed by the user.

11.8.4 Enable Aztec Runes

The Aztec Runes mode is a special mode of the Aztec Code. You can encode only values between 0 and 255. Aztec Runes can be displayed in a very compact way and are highly readable due to Reed Solomon error correction.

11.8.5 Error Correction in % [0-90]

Unlike other barcode types the error correction level of an Aztec Code is not described in pre-defined levels but can be specified in percent of the data amount. Default error correction level is 23% (which is recommended), but it may be in the range from 0 up to 90%.

11.8.6 Structured Append

If you want to “connect” several Data Matrix symbols in order to encode larger quantities of data, you can use “Structured Append”.

11.8.6.1 Use structured append

Activates structured append (symbol-chaining) with this option.

11.8.6.2 Number of all symbols [A...Z]

Enter the total number of chained Data Matrix symbols here. A maximum of 26 symbols may be used within one chain, where “A” stands for 1 and “Z” stands for 26.

11.8.6.3 Index of this symbol [1...16]

A symbol identification number – which is entered in the index field – must be assigned to each Data Matrix symbol. Its value can range from “A” (1) to “Z” (26). This index indicates the order in which the data is joined after the reading/scanning process.

11.8.6.4 Message ID

The Message ID has to be the same for all symbols within a chain.



11.9 Adjust Properties: Codablock-F

Codablock-F is a stacked symbology (like PDF417) based upon the Code 128 character set. Each row consists of a Code 128 symbol, but extended with row indicators (row count and sequence number) and an additional check digit.




Figure 23: Advanced Properties: Codablock-F

11.9.1 Rows [2..44]

Specifies the number of rows used for encoding. The value must be between 2 and 44. Default: the number of lines is calculated automatically depending on the number of input characters.

11.9.2 Columns [4..62]

Defines the number of columns, which are generated. The value must be between 4 and 62. Start-, stop- and line-indicator columns, as well as code subset selectors are not taken into account. Default: the number of columns is calculated automatically depending on the number of input characters.

11.9.3 Row height [1/1000 mm]

Sets the height of an individual row in 1/1000 mm. Default: The row height is calculated automatically.

11.9.4 Separator height [1/1000 mm]

Sets the height of the row separator in 1/1000 mm. Default: The height of the separator is calculated automatically.

11.9.5 Code format

You can choose one of the following formats:

Value	Description
Default	Standard format.
UCC/EAN	Special format defined by UCC and EAN to be used in UCC/EAN applications. Used for encoding so-called Application Identifiers (AIs). A FNC1 is encoded at first position automatically.

Table 12: Codablock-F Code Formats

11.10 Adjust Properties: Data Matrix

- Please note: **TBarCode** always encodes data using the newest ECC200 error correction method.

In this dialog you can set Data Matrix specific properties.




Figure 24: Advanced Properties: Data Matrix

11.10.1 Code Format

Sets the code format which is used for encoding the barcode data.

Value	Description
Default	The standard format of Data Matrix (no special header included).
UCC/EAN	Special format defined by UCC and EAN for encoding Application Identifiers. This format adds the function character FNC1 at 1st position in the symbol.
Industry	supports peculiar industry formats (adds FNC1 at 2nd position).
Macro 05	[>Rs05Gs is encoded at the beginning of the code.
Macro 06	[>Rs06Gs is encoded at the beginning of the code.

Table 13: Data Matrix Code Formats

11.10.2 Symbol Size

Defines the size of the symbol in terms of rows and columns. Possible sizes are "10 x 10" to "144 x 144" modules for a square symbol and "8 x 18" to "16 x 48" for a rectangular symbol. When set to default the minimal square size is used (depending on input data).

11.10.3 Show as Rectangle

Determines if the Data Matrix symbol should be displayed as rectangle (checked) or square (unchecked – default).

11.10.4 Structured Append

If you want to "connect" several Data Matrix symbols in order to encode larger quantities of data, you can use "Structured Append".

11.10.4.1 Use structured append

Activates structured append (symbol-chaining) with this option.

11.10.4.2 Number of all symbols [2...16]

Enter the total number of chained Data Matrix symbols here. A maximum of 16 symbols may be used within one chain.

11.10.4.3 Index of this symbol [1...16]

A symbol identification number – which is entered in the index field – must be assigned to each Data Matrix symbol. Its value can range from 1 to 16. This index indicates the order in which the data is joined after the reading/scanning process.

11.10.4.4 File-ID [1...64516]

The File ID has to be the same for all symbols within a chain.




11.11 Adjust Properties: MaxiCode

MaxiCode represents data by drawing hexagonal items which are arranged around a circular center (bull's eye). The internal data structure is regulated by different modes. The "Structured Carrier Message" mode was defined by the United Parcel Service UPS®. Data can be encoded with two different error correction levels: SEC (= Standard Error Correction) and EEC (= Enhanced Error Correction).

MaxiCode is very flexible. With structured append you can divide larger quantities of data into several MaxiCode symbols (see also section 11.4, Property Page "Multiple Barcodes") – they are then re-joined by the scanner.

The maximum data capacity of one symbol is 93 characters. The actual quantity of the utilizable data depends on the selected mode, the number of special characters, and whether numeric sequences are used or not (numeric sequences can be encoded using less space than ASCII data). Last but not least the error correction level influences data capacity.



The image shows the 'MaxiCode Properties' dialog box. It has a title bar with a close button. The main area contains several sections:

- Mode:** A dropdown menu currently set to '4 - Standard symbol'.
- Undercut [0..100 %]:** A text input field with a 'Default' checkbox checked.
- Preamble options:** A section with a 'Use preamble' checkbox (unchecked) and a 'Preamble date [0..99]:' text input field containing '96'.
- Structured append:** A section with a 'Use structured append' checkbox (unchecked), a 'Number of all symbols [2..8]:' text input field containing '2', and an 'Index of this symbol [1..8]:' text input field containing '1'.
- Structured carrier message (SCM):** A section with three text input fields: 'Service class [0..999]:', 'Country code [0..999]:', and 'Postal code [9 digits]:'.

 At the bottom right are 'OK' and 'Cancel' buttons.

Figure 25: Advanced Properties: MaxiCode

11.11.1 Mode

Selects the mode for the actual symbol. Default: Mode 4.

Value	Description
Default	Is equal to Mode 4
Mode 2	SCM Numeric ► Structured Carrier Message with 9 digits Postal Code (digits only)
Mode 3	SCM Alphanumeric ► Structured Carrier Message with up to 6 characters Postal Code (alphanumeric characters)
Mode 4	No SCM, encoding of numeric and alphanumeric characters (incl. Standard Error Correction)
Mode 5	Full EEC – like mode 4 but with maximum error correction (safer, but less data possible)

Table 14: MaxiCode Compaction Modes

11.11.2 Undercut [0..100 %]

The undercut influences the diameter of the hexagonal barcode elements. In new applications it is recommended (according to the AIM standard) to use an undercut setting of 75% (default).

11.11.3 Preamble Options

Used in particular open system standards. Under "Preamble date" the last two digits of a year can be entered. They are automatically inserted into the data stream in a predefined place.

The preamble can also be specified by escape sequences in the "Barcode data" (alias *Text* property). To learn more about this option, please refer to the Barcode Reference (see Appendix A).

11.11.3.1 Use Preamble

Enables the preamble mode if checked.

11.11.3.2 Preamble date (0...99)

This is the value of the preamble year to be encoded in the MaxiCode symbol.

11.11.4 Structured Append

Structured append is used for appending multiple MaxiCode symbols to one chain. Therefore some additional header information (total number of barcodes, index) will be included in the barcode symbol.

Using structured append, a large amount of input data which is split up into multiple barcode symbols can be re-joined correctly, even if the barcodes are read in the wrong order.

11.11.4.1 Use structured append

Activate this option if structured append should be activated.

11.11.4.2 Number of all symbols [2...8]

The total number of MaxiCode symbols must be specified in this field.

11.11.4.3 Index of this symbol [1...8]

The symbol identification number (index) can be assigned to each MaxiCode symbol. Its value can range from 1 to 8. The index is used for identifying the correct re-joining order.

11.11.5 Structured Carrier Message (SCM)

MaxiCode was originally developed by UPS® (United Parcel Service). The operating modes 2 and 3 (Structured Carrier Message) provide the additional data-fields *Service Class*, *Country Code* and *Postal Code*.

These fields can also be specified by escape sequences in the "Barcode data" (alias *Text* property). For more information, please refer to the Barcode Reference (see Appendix A).

11.11.5.1 Service class [0...999]

Specifies the service class within the SCM (mode 2 or 3).

11.11.5.2 Country code [0...999]

Specifies the country code within the SCM (mode 2 or 3).

11.11.5.3 Postal code [9 digits]

Specifies the postal-code within the SCM (mode 2 or 3).

- Mode 2: up to 9 digits can be specified.
- Mode 3: up to 6 characters (digits and uppercase letters) can be specified.

11.12 Adjust Properties: PDF417

PDF417 divides data content into graphical rows and columns. It is a so-called “stacked symbology”. This property page allows you to change specific settings for PDF417, PDF417 Truncated and MicroPDF417 symbologies.

Figure 26: Advanced Properties: PDF417

► Please take care when modifying these properties. Some settings may result in unreadable barcodes. Always make a test scan in case of doubt!

11.12.1 PDF417

These settings apply for all PDF417 based barcodes (PDF417, PDF417 Truncated, MicroPDF417).

11.12.1.1 Rows [3..90]

Specifies the number of rows for one PDF417 symbol. Values between 3 and 90 are allowed.

Default: the number of lines (rows) is calculated automatically depending on the amount of input data.

11.12.1.2 Row height [1/1000 mm]

Sets the height of an individual row in 1/1000 mm.

Default: the row height is calculated automatically depending on the bounding rectangle and the number of rows.

Some label specifications require a specific ratio between module width and row height.
Example: If a ratio of 1:3 is required you might set the module width to 254 and the row height to 762.

11.12.1.3 Columns [1..30]

Defines the number of columns for one PDF417 symbol. Values between 1 and 30 are allowed. The start-, stop- and line-indicator columns (which are fixed parts of the symbol) are not taken into account.

Default: the number of columns is calculated automatically depending on the number of input characters.

► You should not set both rows AND columns to a constant value!

11.12.1.4 Error Correction Level

Sets the error correction level. Values between 0 and 8 are allowed.

The error correction level defines the number of code words which are used for error recognition/correction. Each PDF417 barcode contains at least two code words:

Level 0: 2 code words. Level 1: 4 code words. Level 2: 8 code words. And so on: Levels 3 to 7 are using 16, 32, 64, 128 and 256 code words. Level 8 uses 512 code words for error correction.

Value	Description
Default	Depending on the amount of input data the error correction level is set to a value between 2 and 5 automatically.
0	Error recognition only (no error correction is possible). 2 code words are used for calculating a check sum.
1	Error correction. 4 code words are used for error correction information.
2	Error correction. 8 code words are used for error correction information.
:	:
8	Error correction. 512 code words are used for error correction information.

Table 15: PDF417 Error Correction Levels

A higher error correction level adds more redundant information to the symbol. Therefore the symbol will require more space for printing. If the symbol is distorted through surface damage, bad printing quality or dirt the error correction information can help to reconstruct the full information contained in the PDF symbol (reconstruction is done by the scanner).

► The error correction algorithm (Reed Solomon) has the following limit for a successful reconstruction of data: $([\text{total number of not decodable characters}] + 2 * [\text{number of read errors}])$ must be smaller than $([\text{number of error correcting code words}] - 2)$.

11.12.1.5 Encoding Mode

Choose the encoding mode of the barcode.

Value	Description
Normal (Default)	Analyzes the input data. Depending on the input data either "text", "numeric" or "binary compaction" mode is used in order to keep the resulting symbol as small as possible.
Binary Compaction	Uses binary mode for encoding (no input data analysis). This mode is recommended if you want to encode binary input data.

11.12.2 MicroPDF417

These settings apply for the MicroPDF417 symbology only.

11.12.2.1 Mode

Specifies how data is encoded when using Micro PDF417. In most cases the “Default” or the “Binary” mode is the best choice. Some decoders may not support all modes listed here. – Please, check with your scanner first.

Value	Description
Normal (Default)	Analyzes the input data. Depending on the input data either “text”, “numeric” or “binary compaction” mode is used in order to keep the resulting symbol as small as possible.
UCC/EAN-128 Emulation	UCC/EAN-128 emulation mode. Transmit JC1 or JL3. Use compaction for Application Identifier (AI) "01" + 14 digits.
Code128 Emulation	Code-128 emulation mode. Transmit JC2 or JL4.
Code128 FNC2 Emulation	Code-128 with FNC2 on first position will be emulated.
Linked UCC/EAN-128	Linked UCC/EAN-128 emulation. Transmit JC1 or JL3. This mode links the MicroPDF symbol with a linear (1D) symbol. The linked symbol may be required for a successful scan. The symbol can be encoded with better compaction when using one of the following orders for Application Identifiers (AIs): <ul style="list-style-type: none"> ▪ date (AI 11, 13, 15 or 17) + lot number (AI 10) + other AIs (optional). ▪ date (AI 11, 13, 15 or 17) + serial number (AI 21) + other AIs (optional). ▪ date (AI 11, 13, 15 or 17) + other AIs (optional). Note: This mode is not used with UCC/EAN Composite Symbology, which uses linked symbols as well.
05 Macro	The preamble [(> RS 0 5 GS precedes the barcode data.
06 Macro	The preamble [(> RS 0 6 GS precedes the barcode data.
CC-A Data Mode	Uses Base-928 compaction and processes input data as byte array.
CC-B Data Mode	Uses binary compaction (Base-900). The barcode data is prefixed with a reserved code word.

Table 16: Micro PDF417 Compaction Modes

11.12.2.2 Version

Specifies the “size” of the symbol in terms of codeword columns and MicroPDF417 rows.

11.12.3 Macro PDF417 (structured append)

Macro PDF417 is used for connecting multiple PDF417 symbols (PDF417, PDF417 Truncated or MicroPDF417) into one chain. For each symbol of the chain you can specify

- the “Segment Index” of the actual symbol
 (“Last symbol” specifies, that the actual symbol is the last symbol in the chain),
- the “File ID” (which identifies one chain of symbols),
- optional information:
 - File name
 - Segment count
 - Time stamp
 - Sender
 - Addressee
 - File size
 - Checksum (CCITT-16)

11.13 Adjust Properties: QR-Code

The QR-Code is a 2-dimensional matrix symbology (like Data Matrix). It has a remarkable data capacity of up to 3000 ASCII characters or 7000 digits. The QR-Code symbology was designed to read a lot of data within a minimum of time (QR-Code means Quick Response Code).

Figure 27: Advanced Properties: QR-Code

11.13.1 Format / Application Indicator

You can choose from:

Value	Description
Default	The standard format of QR-Code.
UCC/EAN	Special format defined by UCC and EAN. Used for encoding so-called Application Identifiers. FNC1 is added at first position.
Industry	For special industry formats. If you choose this value, you have to fill in an Application Indicator (2 digits or 1 letter). It determines which industry format the barcode data corresponds to. FNC1 is inserted at second position.

Table 17: QR-Code Formats

11.13.2 Symbol Version (Size)

Defines the version (= size) of the QR-Code symbol. Possible values range from "(1) 21 x 21" to "(40) 177 x 177" modules. If the property is set to default, the size is computed automatically based on the length of the barcode data.

11.13.3 Error Correction Level

Defines the error correction level.

Value	Description
(L)ow	Lowest level. Data recovery capacity is approximately up to 7%.
(M)edium	Up to 15%
(Q)uartil	Up to 25%
(H)igh	Highest level. Up to 30%

Table 18: QR-Code Error Correction Levels

11.13.4 Mask Pattern

Selects the mask pattern which is applied to the barcode symbol (XOR masking). The goal of the mask pattern is to distribute the bar-space transitions evenly over the symbol in order to improve the readability of the barcode.

Value	Description
Default	Selects the mask pattern automatically (recommended).
0..7	Selects one of the mask patterns (0 to 7) manually. Manual selection may be useful, if you want to generate many symbols within minimal computation time. The algorithm for identifying the optimal mask automatically is complex (and resource consuming). However, the readability of the barcode may suffer when using manual selection.

Table 19: QR-Code Mask Patterns

11.13.5 Compaction

QR-Code can compact dedicated Multi Byte character sets from 16 bit representation into 13 bit encoding. This property enables the compaction of Kanji or Simplified Chinese characters into 13-bit values.

ActiveX controls are using the Unicode™ character set. Depending on the *Code Page* property, the Unicode input is converted to the corresponding encoding.

If you use one of the available compaction modes, please make sure that the Unicode input is converted to either Shift JIS X 0208 (Kanji) or GB2312 (Simplified Chinese). Also make sure that your decoder (scanner) can deal with these compaction modes.

Value	Description
Default	Default multi byte character compression. Depends on specified <i>Code Page</i> .
None	No multi byte character compression.
Kanji compaction	Enables Kanji character compaction. Input data must be supplied in Multi Byte character set Shift JIS X 0208 (see <i>Code Page</i>). Compaction of Kanji characters is done according to ISO/IEC 18004 (and AIM ITS/97-001) specification.
Chinese compaction	Enables Chinese character compaction. Input data must be supplied in Multi Byte character set GB2312 (see <i>Code Page</i>). Compaction of Chinese characters is done according to GB/T 18284-2000). Please note that this compaction mode is not supported by all decoders.

Table 20: QR-Code Compaction Modes

11.13.6 Structured Append

If you want to connect several QR-Code symbols (for encoding larger quantities of data) you can use structured append.

11.13.6.1 Use Structured Append

Activates structured append (symbol-chaining).

11.13.6.2 Parity Byte [0...255]

Chained QR-Code symbols are identified by the parity byte. The parity byte must be identical in all symbols of a chain.

- The value of the parity byte depends on the barcode data for the complete chain. To calculate its value you can use the method *QRCode.StructAppParity()* which is available in the ActiveX interface.
For more information about the ActiveX interface and its available methods, please refer to the developer manual (see Appendix A).

11.13.6.3 Number of all Symbols [2...16]

Enter the total number of chained QR-Code symbols here. A maximum of 16 symbols may be used within one chain.

11.13.6.4 Index of this Symbol [1...16]

A symbol identification number – which is entered in the index field – must be assigned to each QR-Code symbol. Its value can range from 1 to 16. This index indicates the order in which the data is joined after the reading/scanning process.



11.14 Adjust Properties: Composite/RSS

In this menu you can adjust the parameters for the “EAN.UCC Composite Symbology” and for the “RSS Expanded Stacked” symbology.




Figure 28: Advanced Properties: Composite/RSS

11.14.1 Composite Component

Selects the 2D composite component in order to generate an EAN.UCC Composite Symbology.

Value	Description
Default (None)	Composite Symbologies are disabled
Auto (CC-A/B/C)	Automatically choose CC-A, CC-B or CC-C type depending on the length of the input data
CC-A	Use composite component A (CC-A). CC-A is a variant of the MicroPDF417 symbology with a unique combination of row address patterns (RAP). It is the smallest variant of the 2-dimensional composite component. Up to 56 characters can be coded (also alphanumeric) with 3 to 12 rows and 4 columns.
CC-B	Use composite component B (CC-B). CC-B is a subset of the MicroPDF417 Symbol which is identified by the code word 920. CC-B will be chosen automatically when CC-A has not enough capacity (in Auto-mode). CC-B encodes up to 338 Characters (alphanumeric) in 3 to 12 rows and 2 to 4 columns.
CC-C	Use composite component C (CC-C). The CC-C structure is a PDF417 Symbol which is identified by the internal code word 920 (920 is the first code word after the symbol length indicator). The CC-C structure can be used as a 2D composite component of a UCC/EAN-128 Composite Symbol. It has the largest data capacity among the composite symbologies. It encodes numbers and alphanumeric characters with up to 2361 characters length in 3 to 30 rows. It uses up to 30 data error checking code columns.

Table 21: Composite Component Format

- You can add Composite Components to the following symbologies: EAN-8, EAN-13, UPC-E, UPC-A, RSS family and EAN-128. – CC-C is available for UCC/EAN-128 only!

11.14.1.1 Data Input for the EAN.UCC Composite Symbology

If the composite component is enabled, the data for the 2D composite component has to be separated from the linear component with a vertical bar “|”.

Example: 1234567890123|CompositeData

If a symbology has a fixed data length (such as RSS-14) the vertical bar is optional. All remaining characters (after the 14th digit) will be encoded into the 2D component automatically.

11.14.2 Segments per Row

For the RSS Expanded Stacked symbology you can adjust the number of data segments per row. Allowed are even values between 2 and 22. This parameter influences the width to height ratio of the barcode symbol.



12 Licensing

12.1 License Types

Please check out <http://www.tec-it.com/order> for available license types and pricing.

Single licenses are bound to exactly one machine. If you are interested in a single license, please tell us the so-called "*System ID*" of the target computer. You can find the System ID in the licensing dialog (see below).

12.2 Entering your License Data


After receiving your license data, enter it in the license dialog. You can also pass the license information via program code (software developers) – see section 8.5.

- **Please enter the license data exactly as you received it from TEC-IT!**
Spacing and upper/lower case letters are significant. To avoid typographical errors, please insert the data using "copy and paste" from the email containing your license data whenever possible.

12.2.1 License Dialog

For entering the license data right-click on the inserted **TBarCode** object and select **TBarCode-Object ► License** from the pop-up menu.

The following dialog will appear:



- ① This is the *System ID* of your Computer.

Under "*Product*" select the product that you have purchased: You can select:

- TBarCode 1D (standard)
- TBarCode 2D (incl. 2D symbologies).

In the field "*Licensee*" enter the name that you entered as licensee at the time of your purchase (or the name that was assigned to you when you received the license key).

Under "*Kind of License*" select the kind of license that you have purchased. You can select:

- Single (Einzellizenz)
- Site (Firmenlizenz)
- Developer (Entwicklerlizenz).

Under "*Number of Licenses*" enter the number of licenses that you have purchased.

In the field "*Your license-key*" enter the license key exactly as you received it from TEC-IT.

13 Contact and Support Information

TEC-IT Datenverarbeitung GmbH

Address: Wagnerstr. 6
AT-4400 Steyr
Austria/Europe
Phone: +43 / (0)7252 / 72 72 0
Fax: +43 / (0)7252 / 72 72 0 – 77
Email: <mailto:support@tec-it.com>
Web: <http://www.tec-it.com>

AIX is a registered trademark of IBM Corporation.

HTML, DHTML, XML, XHTML are trademarks or registered trademarks of W3C, World Wide Web Consortium, Laboratory for Computer Science NE43-358, Massachusetts Institute of Technology, 545 Technology Square, Cambridge, MA 02139.

JAVA® is a registered trademark of Sun Microsystems, Inc., 901 San Antonio Road, Palo Alto, CA 94303 USA.

JAVASCRIPT® is a registered trademark of Sun Microsystems, Inc., used under license for technology invented and implemented by Netscape.

Microsoft®, Windows®, Microsoft Word®, Microsoft Excel® are registered trademarks of Microsoft Corporation.

Navision is a registered trademark of Microsoft Business Solutions ApS in the United States and/or other countries.

Oracle® is a registered trademark of Oracle Corporation.

PCL® is a registered trademark of the Hewlett-Packard Company.

PostScript is a registered trademark of Adobe Systems Inc.

SAP, SAP Logo, R/2, R/3, ABAP, SAPscript are trademarks or registered trademarks of SAP AG in Germany (and in several other countries).

Unicode is a trademark of Unicode Inc.

All other products mentioned are trademarks or registered trademarks of their respective companies. If any trademark on our web site or in this document is not marked as trademark (or registered trademark), we ask you to send us a short message (<mailto:office@tec-it.com>).



Appendix A: Related Downloads

A.1 Developer Manuals

For software developers **TBarCode** provides additional documents:

- Developer Manuals
Descriptions on how to use **TBarCode** in development environments (IDEs) like Microsoft Visual Studio, Borland Delphi, Borland C++ Builder, Sybase Power Builder, ASP, .NET and more...
- Developer References
Detailed descriptions of the **TBarCode** programming interface (API) with all methods, properties, enumerations and events.

These documents are included in the setup (Start Menu: *TEC-IT TBarCode 8 ► Developer Manuals*).

A.2 Sample Applications

TEC-IT provides a number of sample applications which allow customers to start with the development of their own applications and/or documents as fast as possible.

Sample applications are included in the **TBarCode8** setup (Start Menu: *TEC-IT TBarCode 8 ► Examples*) or can be downloaded from the TEC-IT web site <http://www.tec-it.com> (download area).

► Make sure **TBarCode** was installed before trying to run any sample application!

A.3 Barcode Reference

The document "Barcode Reference" provides an overview over supported barcode types and gives additional information on how to use them.

The following issues are discussed:

- Supported Barcode Symbolologies
(with detailed information on each barcode type)
- Check Digits
(general information and available check digits methods)
- Print Ratio and Ratio Hints (or Ratio Format)
- Format Strings
- Escape Sequences and Control Characters
- Application Identifiers
- MaxiCode and UPS standards
- And more...

The Barcode Reference is available as separate document on the TEC-IT web-site <http://www.tec-it.com> ► Support ► Knowledge Base

The direct URL is as follows:

http://www.tec-it.com/download/PDF/Barcode_Reference_EN.pdf.

Appendix B: FAQ

B.1 General

If you have questions not covered in these FAQ, you can also check our website <http://www.tec-it.com/FAQ> or contact our support team: <mailto:barcode@tec-it.com>.

B.2 Mail Merge Documents with Barcodes?

You can do this by running a Word VBA Macro. The macro provides the functionality for adding barcodes to a mail merge document. The Macro *"BarcodeSeries"* is contained in a dot file, which must be included to your mail merge document.

The Macro File (BarcodeSeries.dot) is part of the samples, which are installed with the **TBarCode OCX** setup. If you can't get it with the setup you can download it from <http://www.tec-it.com> or request it by email from support@tec-it.com

